



# **Delinea Mobile**

**Administrator Guide**

**Version: 2.2.x**

**Publication Date: 4/1/2024**

## Delinea Mobile Administrator Guide

Version: 2.2.x, Publication Date: 4/1/2024

© Delinea, 2024

### Warranty Disclaimer

DELINEA AND ITS AFFILIATES, AND/OR ITS AND THEIR RESPECTIVE SUPPLIERS, MAKE NO REPRESENTATIONS ABOUT THE SUITABILITY OF THE INFORMATION CONTAINED IN THE DOCUMENTS AND RELATED GRAPHICS, THE SOFTWARE AND SERVICES, AND OTHER MATERIAL PUBLISHED ON OR ACCESSIBLE THROUGH THIS SITE FOR ANY PURPOSE. ALL SUCH MATERIAL IS PROVIDED "AS IS" WITHOUT WARRANTY OF ANY KIND. DELINEA AND ITS AFFILIATES, AND/OR ITS AND THEIR RESPECTIVE SUPPLIERS, HEREBY DISCLAIM ALL WARRANTIES AND CONDITIONS WITH REGARD TO SUCH MATERIAL, INCLUDING ALL IMPLIED WARRANTIES AND CONDITIONS OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE, TITLE AND NON-INFRINGEMENT.

THE MATERIAL PUBLISHED ON THIS SITE COULD INCLUDE TECHNICAL INACCURACIES OR TYPOGRAPHICAL ERRORS. CHANGES ARE PERIODICALLY ADDED TO THE INFORMATION HEREIN. DELINEA AND ITS AFFILIATES, AND/OR ITS AND THEIR RESPECTIVE SUPPLIERS, MAY MAKE IMPROVEMENTS AND/OR CHANGES IN THE MATERIAL DESCRIBED HEREIN AT ANY TIME.

### Disclaimer of Liability

IN NO EVENT SHALL DELINEA AND ITS AFFILIATES, AND/OR ITS AND THEIR RESPECTIVE SUPPLIERS, BE LIABLE FOR ANY SPECIAL, INDIRECT, OR CONSEQUENTIAL DAMAGES (INCLUDING LOSS OF USE, DATA, PROFITS OR OTHER ECONOMIC ADVANTAGE) OR ANY DAMAGES WHATSOEVER, WHETHER IN AN ACTION OF CONTRACT, NEGLIGENCE, OR OTHER TORTIOUS ACTION, ARISING OUT OF OR IN CONNECTION WITH THE USE OR PERFORMANCE OF SOFTWARE, DOCUMENTS, PROVISION OF OR FAILURE TO PROVIDE SERVICES, OR MATERIAL AVAILABLE FROM THIS SITE.

## Table of Contents

Administrator Guide .....	i
<b>Delinea Mobile Overview .....</b>	<b>1</b>
Multi-factor Authentication .....	1
Biometric Unlock .....	1
Autofill .....	1
<b>Configuring Authentication Profiles and Mobile Sessions .....</b>	<b>2</b>
Mobile App Session Policy .....	3
Configuring Authentication Profiles in Secret Server .....	3
<b>Login Process .....</b>	<b>4</b>
User Authentication .....	4
Biometric Unlock .....	4
Authenticate With the Delinea Mobile Authenticator .....	5
Logging in to the Delinea Mobile App .....	6
Login to the Delinea Platform .....	6
Login to Secret Server .....	9
Multi-Factor Authentication .....	11
Login With Biometric Unlock .....	11
<b>Login Flow for the Delinea Platform Portal (MFA) .....</b>	<b>13</b>
Delinea Platform Login with Browser .....	13
Alternate TOTP Authentication .....	17
<b>Secrets Tab .....</b>	<b>19</b>
Filter by Template .....	20
Enable Autofill .....	21
Delinea Mobile Autofill Considerations on Android Devices .....	26
Browser Compatibility .....	26
Troubleshooting Autofill on Delinea Mobile .....	27
Additional Troubleshooting .....	27
Create a New Secret .....	27
Edit a Secret .....	32
Search for a Secret .....	34
View Secrets .....	36
Accessing Secrets Guarded by MFA .....	39
Accessing Secrets Guarded by DoubleLock .....	42
Secret Workflows .....	44
Secret Check Out .....	44
Check In a Secret .....	46
Check Out a Secret Tied to a Ticketing System .....	48
<b>Folders Tab .....</b>	<b>51</b>
Managing Folders .....	51

## Table of Contents

Add a New Folder .....	51
Add a New Folder From the Folder View .....	54
Open Folders .....	59
Search for Folders .....	61
Search "This" Folder .....	62
Select Folders .....	63
<b>Using the Delinea Mobile Authenticator .....</b>	<b>65</b>
Logging In to the Delinea Platform .....	65
Adding New Passcodes .....	66
Delete a TOTP Code .....	71
Edit Account Information .....	73
<b>Release Notes .....</b>	<b>76</b>
2.2 Release Notes .....	77
Usability Improvements .....	77
Bug Fixes .....	77
2.1.6 Release Notes .....	77
Usability Improvements .....	78
2.1.5 Release Notes .....	78
Usability Improvements .....	78
Bug Fixes .....	78
2.1.4 Release Notes .....	78
Features .....	78
Usability Improvements .....	79
Bug Fixes .....	79
iOS Specific .....	79
2.1.3 Release Notes (iOS Only) .....	79
Bug Fixes .....	80
2.1.2 Release Notes .....	80
Features .....	80
Improvements .....	80
Bug Fixes .....	81
iOS Specific .....	81
2.1.1 Release Notes .....	81
Features .....	81
Bug Fixes .....	81
iOS Specific .....	82
Android Specific .....	82
2.1.0 Release Notes .....	82
Features .....	82
Usability Improvements .....	82
Bug Fixes .....	82
Android Specific .....	82
iOS Specific .....	82

## Table of Contents

2.0.11 Release Notes .....	83
Android Specific .....	83
2.0.10 Release Notes .....	83
Improvements .....	83
Bug Fixes .....	83
Android Specific .....	83
2.0.8 Release Notes .....	83
Improvements .....	83
Bug Fixes .....	84
2.0.7 Release Notes .....	84
Improvements .....	84
Bug Fixes .....	84
Android Specific .....	84
2.0.6 Release Notes .....	84
Improvements .....	84
Bug Fixes .....	84
Android Specific .....	84
2.0.5 Release Notes .....	84
Improvements .....	85
Bug Fixes .....	85
Android Specific .....	85
2.0.0 Initial Release .....	85

## Delinea Mobile Overview

The Delinea Mobile app provides MFA verification for the Delinea Platform as well as portable access to secrets managed in Secret Server. The app supports the use of multiple Secret Server tenants for users that need access to multiple Secret Server tenants. The MFA function also supports biometric data to make the user experience convenient as well as secure. Once logged in, users can view secrets that they have permission to see in their Secret Server vault. Users can create new secrets directly in the mobile app, as well as organize secrets into folders.

The app can also be set as an auto-fill provider in the mobile device and fill in user-names and passwords for matching secrets. It also includes convenient Time-based one-time password (TOTP) capabilities that can be used with sites and web applications that support TOTP-based authentication

Users can download the Delinea Mobile application from the following sources:

- [iOS App Store](#)
- [Google Play Store](#)

## Multi-factor Authentication

The mobile application supports the following MFA mechanisms as used by Secret Server:

- Delinea Mobile Authenticator

## Biometric Unlock

The mobile application supports using biometric authentication in place of usernames and passwords.

- Fingerprint (Android and iOS)
- Facial recognition (iOS only, not all phone/iOS combinations)
- The application will auto-reconnect to Secret Server if the connection is temporarily dropped due to network issues.

## Autofill

When a user enables their mobile device's autofill service and then registers Delinea Mobile with that service, users can launch a web session from a secret on the mobile device and automatically populate username and password login credentials on specified web sites or other mobile applications.

When you select the mobile application or web page and click on the username field you should see a prompt from Delinea Mobile to use the autofill service. Click this option to open the mobile app and log in if necessary, and the app runs a search of your secrets for:

- Browser web site - to search for any secret that has the same Domain value in the URL
- Other mobile application - to search for any secret that has the same name or URL value as the name of the mobile application that is being filled.


## Configuring Authentication Profiles and Mobile Sessions

Users can also choose to manually modify the search value and run it again. Once the list of Secret Server Secrets has been returned, you can select which one you want to use and the autofill service will fill those credentials in the related username and password fields.

 **Note:** Currently the autofill service supports only the username and password fields.

## Configuring Authentication Profiles and Mobile Sessions

Delinea Mobile can be used as an MFA mechanism for logging into the Delinea Platform. If you would like to use Delinea Mobile as part of any authentication profile, check the *Mobile Authenticator* box when setting up that profile.



The *Mobile Authenticator* and other selected authentication mechanisms will appear on the user's authentication profile card.

### Art Decco's Login Profile

2 challenges  
12 Hours pass-through duration

---

**Challenge 1**

- Password
- Mobile authenticator
- FIDO2 authenticator

**Challenge 2**

- Password
- Mobile authenticator
- OATH OTP client
- FIDO2 authenticator
- Security questions

[Edit profile](#)

For more information on authentication profiles, please refer to the [Delinea Platform documentation](#).

## Mobile App Session Policy

Users can set the desired session length for Delinea Mobile (in days) inside the Delinea Platform. When the session length is reached, the user will have to re-authenticate with the Platform. While the default session length is set to 14 days, session lengths can be configured to last within the following ranges:

- Minimum - 1 day
- Maximum - 90 days

For more information, please refer to the [Delinea Platform documentation](#)

## Configuring Authentication Profiles in Secret Server

Currently, Secret Server does not offer authentication profiles specific to Delinea Mobile. Therefore, you will have to adjust the *Web Service Settings* inside Secret Server. Delinea Mobile uses these settings for the token lifespan and the number of refresh tokens which affects how long Delinea Mobile can remain logged into Secret Server.

For more information on how to configure these settings, please refer to the [Secret Server documentation](#)



# Login Process

- [Login Process](#)
- [User Authentication](#)


## User Authentication

Delinea Platform supports multi-factor authentication (MFA) via a variety of authentication mechanisms. If a user selects Mobile Authenticator when challenged for additional authentication, they will be required to respond to a push notification (or enter a code) on their registered device.

## Biometric Unlock


Biometric unlock is enabled by default. Delinea recommends using either facial recognition (iOS only) or fingerprint ID (Android and iOS) in place of username and password credentials.

1. Tap on your profile image and tap **Settings**



2. Enable FaceID for iOS devices or fingerprint identification for Android


## Login Process



### Authenticate With the Delinea Mobile Authenticator

When Mobile Authenticator is selected as the additional authentication method you will be prompted to respond to a push notification (or enter a one-time passcode) on the registered device.

## Login Process




## Logging in to the Delinea Mobile App

The Delinea Mobile app can be used to log in to the Delinea Platform and Secret Server.

### Login to the Delinea Platform

1. At the login screen, enter your Delinea Platform tenant URL

## Login Process



2. Enter your Username

## Login Process



3:03

[←](#)

# Delinea

Defining the Boundaries of Access

## Log in

Username [Forgot username](#)


Next

**Delinea**

©2025 Delinea [Terms & Conditions](#) [Privacy Policy](#)

3. Enter your Password and select an authentication method

## Login Process



1:10

**Delinea**  
Defining the Boundaries of Access

Log in

mobile@platform.demo

Password [Forgot password](#)

Authentication method

How do you do?

Next

[Start over](#)


**Delinea**

4. Tap **Next** to log in.
5. If multifactor authentication is enabled, you will need to complete it as per the selected authentication method

## Login to Secret Server


1. At the login screen, enter your Secret Server URL

## Login Process



2. Log into Secret Server or authenticate through your identity provider

## Login Process



### 3. Login with your Username and Password

## Multi-Factor Authentication

Delinea Mobile supports the following MFA mechanisms used by Secret Server:

- DUO - Push
- DUO - Phone call

## Login With Biometric Unlock


Delinea Mobile supports biometric unlock for devices with the following operating systems:

- iOS 14 and newer (FaceID)
- Android 10 and newer (TouchID)


If biometric unlock fails, users will have the option of entering their device PIN code to login



## Login Process



## Login Flow for the Delinea Platform Portal (MFA)




## Login Flow for the Delinea Platform Portal (MFA)

The Delinea Mobile app can be used as an MFA mechanism for logging in to the Delinea Platform. This section will describe the login flow for the Delinea Platform portal, responding to notifications and using the built-in TOTP code.


### Delinea Platform Login with Browser

1. Enter your Delinea Platform tenant URL into your web browser.
2. At the *Log In* screen, enter your *Username* and click **Next**

## Login Flow for the Delinea Platform Portal (MFA)



3. Select *Mobile Authenticator* as your authentication method and click **Next**




## Login Flow for the Delinea Platform Portal (MFA)



**Note:** The Mobile Authenticator needs to be enabled in your tenant authentication profile. Click [here](#) to learn more.


4. You will receive a notification on your registered device.

Login Flow for the Delinea Platform Portal (MFA)



## Login Flow for the Delinea Platform Portal (MFA)

5. Tap the notification and complete the biometric prompt to navigate to the authentication prompt.



### Platform Login Request mycompany.delinea.app

🕒 10:13 AM

👤 Art Decco


✖ Deny


✔ Approve

## Alternate TOTP Authentication

You also have the option of entering the 8-digit TOTP code from the Authenticator tab into the MFA screen to complete the login.

# Login Flow for the Delinea Platform Portal (MFA)






## Secrets Tab

The Secrets tab offers several options enabling users to view secrets. The Search feature (magnifying glass icon) enables users to search for secrets by name. Four tabs on the Secrets page enable users to view their secrets four different ways:

- **All:** all secrets the user has view access to
- **Favorites:** secrets the user has designated as "Favorite"
- **Shared:** secrets shared between the user and other users




## Secrets Tab



The Secrets tab displays a prominent Add icon  at the very top enabling users to quickly add folders and secrets.


Clicking on a secret opens access to options that are generated dynamically, meaning that the options presented match the actions the user is likely to want to make at that moment. These actions can include view, delete, edit, cache, refresh cache, remove from cache, check in or check out, favorite or unfavorite, request access. etc.

### Filter by Template

Users can filter secrets by templates by tapping on the "filter menu"  at the top of the screen.

A new screen will appear allowing you to select the templates by which you want to filter.

## Secrets Tab




Tap on the desired template to apply the filter.

## Enable Autofill

To enable Delinea Mobile to autofill credentials for apps and websites, follow these steps:


1. Open your device settings and tap *Passwords*

## Secrets Tab




2. Tap *Password Options*

## Secrets Tab




3. Enable the *Autofill Passwords* toggle

## Secrets Tab





4. Select *Delinea Mobile*

## Secrets Tab



5. You will see a confirmation screen that autofill has been enabled



 **Note:** Users first need to complete Delinea Mobile's biometric unlock before attempting to autofill values from Delinea Mobile.

## Delinea Mobile Autofill Considerations on Android Devices

Delinea Mobile offers a strong autofill feature to simplify user interactions. However, certain considerations exist, especially regarding Android versions, vendors, and browser compatibility. Since Android 13, battery optimizations have been introduced, affecting autofill functionality on specific web browser apps. Users may experience variations in autofill behavior on Android versions 13 and higher. Additionally, different vendor implementations may impact how Delinea Mobile autofill works.

### Browser Compatibility

To ensure a seamless autofill experience, consider using supported browsers like Firefox or DuckDuckGo. These browsers leverage Android's native autofill services, providing compatibility with Delinea Mobile's autofill

## Secrets Tab

functionality regardless of optimization settings.

## Troubleshooting Autofill on Delinea Mobile

### Pixel Devices

For Pixel devices, follow these steps:

1. Change Delinea Mobile's **Battery Usage Policy** to **Unrestricted** in your device settings.
2. Turn off the **Use Battery Saver** option to ensure optimal autofill performance.

### Samsung Devices

Samsung devices may have aggressive optimizations. Users can try the following steps:

1. Turn off the **Adaptive Battery** option in the device app settings.
2. Turn off the **Put unused apps to sleep** setting to prevent interference with Delinea Mobile's autofill.

While these adjustments may help, it's recommended to use a supported browser for the best autofill experience on Samsung devices.

### Additional Troubleshooting

For more information please see [Don't kill my app!](#) for more troubleshooting tips for your specific vendor or version of Android.


## Create a New Secret

To create a new secret:

1. Tap the "plus" at the top of the screen





## Secrets Tab



2. Tap **New Secret**


## Secrets Tab




 New Folder

3. Enter the *Parent Folder* and *Secret Template*. In this particular case, the chosen template is *Azure AD Account*.

## Secrets Tab




4. Tap **Continue**
5. Enter the secret details. The secret detail fields you will see will depend on the secret template you selected in Step 3.



6. Tap **Save**
7. Your secret has been created.


## Secrets Tab



## Edit a Secret


To edit a secret, simply tap on the secret you would like to edit. Click the menu icon next to each field inside the secret.

## Secrets Tab



If you have the necessary permissions, you will see an option to edit a particular field. In this case, the "Host" URL.


## Secrets Tab



## Search for a Secret

To search for a specific secret, simply tap on the "magnifying glass" icon.



## Secrets Tab



Start typing the name of the secret in the search field and the app will filter the results in real time.




## Secrets Tab



## View Secrets


You can view a secret by simply tapping on the secret.

## Secrets Tab




Alternatively, you can tap on the menu icon to the right of the secret and then tap **Details** in the popup menu.

# Secrets Tab




## Secrets Tab





### Accessing Secrets Guarded by MFA

Delinea Platform users can access secrets guarded by MFA through Delinea Mobile. When a user attempts to access a secret guarded by MFA, they will see a message that they must complete an additional MFA challenge:



After clicking **Challenge**, users will be prompted to complete the MFA challenge using the authentication method of their choice:






### Accessing Secrets Guarded by DoubleLock

To access secrets guarded by DoubleLock directly from Delinea Mobile:


## Secrets Tab

1. Tap on the secret you would like to access. The DoubleLock screen appears.



2. Enter your DoubleLock password and tap **Continue**.
3. After you enter the correct password, you will be granted access to the secret.






## Secret Workflows

### Secret Check Out


Users can check out a secret from Secret Server directly from Delinea Mobile. To check out a secret:

## Secrets Tab

1. Tap on the secret you would like to check out.
2. The check out screen appears.




3. Tap **Check Out**

 **Note:** If secret check out requires approval, the required users will need to approve the check out.

## Secrets Tab

4. Users will gain access to the secret. The secret state will change to **checked out**.




## Check In a Secret


To check a secret back in:

## Secrets Tab

1. Click on the more options menu at the top of the screen



2. Tap **Check In**




### Check Out a Secret Tied to a Ticketing System

To check out a secret tied to a ticketing system:


## Secrets Tab

1. Tap on the desired secret. The ticket window appears.



The screenshot shows a mobile application interface for Salesforce. At the top, the status bar displays the time 8:48, signal strength, Wi-Fi, and battery icons. Below the status bar is a dark blue header with a back arrow, a star icon, and a menu icon. The word "Salesforce" is displayed in white text. The main content area is white and features a lock icon at the top center, followed by the text "Complete ticket to view". Below this, there is a "Ticket system" dropdown menu with "TS Requires Either" selected. Underneath is a "Work Order #" text input field. The "Reason to view" section contains a large, empty text area. At the bottom of the form, it says "Send as evgen.brovchenko@delinea-mobile" and a purple "Continue" button.

2. In the "Ticket System" dropdown select the ticket system with the needed fields.



3. Fill in all of the required fields and tap **Continue**.
  4. The secret is now checked out.
-

## Folders Tab

This section contains information on:

- [Adding a new folder](#)
- [Opening a folder](#)
- [Searching for folders](#)
- [Selecting folders](#)


## Managing Folders

The Delinea Mobile app can be used to search for folders, navigate within folders and create new folders.

Learn more about Folders in the [Secret Server documentation](#)


### Add a New Folder

Users can add a new folder from the **Secrets** tab:

1. Tap the  icon on the top of the screen:




## Folders Tab



### 2. Tap **New Folder**


## Folders Tab



 **Note:** The *New Folder* menu item only appears if you have permissions to create a new folder.

3. The **New Folder** screen will appear

## Folders Tab




4. Select the parent folder that will contain the folder you are creating
5. Enter the name of the new folder you need to create

### Add a New Folder From the Folder View


1. Navigate to the folder view by clicking the folder icon

## Folders Tab



2. Click **New Folder**


## Folders Tab



 **Note:** The *New Folder* menu item only appears if you have permissions to create a new folder.


3. The *Folder* screen will appear

## Folders Tab




- 
4. Select the parent folder that will contain this subfolder

## Folders Tab



5. Enter the name of the new folder you need to create

## Folders Tab




## Open Folders

To open a folder, tap on the folder icon in the Secrets tab




## Folders Tab



A list of folders will appear:

## Folders Tab




---

Simply tap on any folder to open it. Users can also create new folders by tapping on the **Plus** icon at the top of the page.


### Search for Folders

To find a specific folder, simply start typing the folder name in the search bar and the system will filter the results in real-time. In the results list you will also see any subfolders and secrets matching your search criteria.

## Folders Tab




Personal Folders



### Search "This" Folder

You can search a folder to find a particular subfolder or secret by typing in a name of the subfolder or secret in the search bar. Tap the < icon in the search input to return to the to the default folders view.


## Folders Tab



### Select Folders

You can select any folder by simply tapping on it. The folder contents will open up and you will see all of the subfolders contained inside.

## Folders Tab




---

The selected folder's name will be displayed in the header. Tapping the < icon navigates user up the folder tree one level or back to to the root if only one level down.

If there are no subfolders, you will see the secrets that are in the folder. If a folder is empty, you will see the notification **This folder is empty**.

## Using the Delinea Mobile Authenticator



---

## Using the Delinea Mobile Authenticator

You can use the Delinea Mobile Authenticator to login to the Delinea Platform as well as other portals requiring multi-factor authentication.


### Logging In to the Delinea Platform

You can log in to the Delinea Platform using the TOTP code found in the Delinea Mobile Authenticator. Please refer to [Alternate TOTP Authentication](#) for more information.

## Adding New Passcodes


Users logging in to portals requiring multi-factor authentication can use TOTP codes generated by Delinea Mobile as an authentication method. To add a new code:

1. Open the Delinea Mobile app and tap **Authenticator**




2. Tap **Add Passcode**

## Using the Delinea Mobile Authenticator




3. If you have a QR code, you can scan the QR and Delinea Mobile will automatically create a TOTP code.

 **Note:** You will need to authorize Delinea Mobile to access your smartphone camera to use this option.




## Using the Delinea Mobile Authenticator




Alternatively, you can select **Manual Setup**

## Using the Delinea Mobile Authenticator





4. If you decided to setup the TOTP code manually, enter the *Issuer*, *Account Name* and *Authentication Key*. Tap **Save Passcode** when done.



## Using the Delinea Mobile Authenticator

5. If you would like to edit the *Key Algorithm*, *OTP Digits* and the time period in (in seconds) for OTP code validity, tap **Advanced Options**

 **Note:** Do not change these settings unless instructed by your service provider.




---

## Delete a TOTP Code

If you would like to delete a TOTP code:


## Using the Delinea Mobile Authenticator

1. Tap the *More Options* menu on the TOTP code:



2. Tap **Delete Account**

## Using the Delinea Mobile Authenticator




### Edit Account Information

To edit the account information:

1. Tap the *More Options* menu
2. Tap **Edit Account Info**

## Using the Delinea Mobile Authenticator




3. Tap the *More Options* menu to edit the fields.

## Using the Delinea Mobile Authenticator





## Release Notes




Cancel

Issuer

Save

Art Decco's Company



## Release Notes

- [2.2 Release Notes](#)
- [2.1.6 Release Notes](#)
- [2.1.5 Release Notes](#)
- "2.1.4 Release Notes" on page 78
- "2.1.3 Release Notes (iOS Only)" on page 79
- "2.1.2 Release Notes" on page 80
- "2.1.1 Release Notes" on page 81

## Release Notes

- "2.1.0 Release Notes" on page 82
- [2.0.11 Release Notes](#)
- [2.0.10 Release Notes](#)
- [2.0.8 Release Notes](#)
- [2.0.7 Release Notes](#)
- [2.0.6 Release Notes](#)
- [2.0.5 Release Notes](#)
- [2.0.0 Release Notes](#)

## 2.2 Release Notes

*January 23rd, 2024*

### Usability Improvements

- Users can request approval for a secret from the Delinea Mobile app.
- Delinea Mobile updated the visual styles for the UI Secret Details screen.
- When users back out of the Secret Details page, they will return to their original position in the secrets list, rather than starting back at the top of the page.
- Delinea Mobile has implemented a floating action button on the secret list screen to quickly add new secrets and folders.
- Delinea Mobile resolved security issues in 3rd party libraries by updating the libraries to newer versions.
- The expiration bar on the Secret Details screen was removed from the navigation bar.

### Bug Fixes

- Secrets that should have been excluded from search results showed in the search results.
- In Secret Server, despite setting the token expiration to Unlimited, users had to log in to the Delinea Mobile app every time they closed and reopened the app.
- The feedback form would jump to the top of the screen when the user started typing, and the text box would disappear if the user selected an emoji.
- The Secrets folders were not sorting in alphabetical order.

## 2.1.6 Release Notes

*December 22nd, 2023*

## Usability Improvements

- Upgraded third party libraries to resolve security issues.
- Added a link in the autofill instructions for more information about troubleshooting autofill issues on Android. (Android only)

## 2.1.5 Release Notes

December 15th, 2023

### Usability Improvements

- Improvements were made to the autofill biometric warning, such as, a title was added, a link to the Settings page was added and the dismiss button style was changed.
- Increased the space between the password header and password text in View Password.
- Fixed the margins on the Secret screen and the Folder screen to be consistent.

### Bug Fixes

- Fixed an issue where Delinea Mobile would not allow users to login with Okta Federation.
- Fixed an issue where logging in with Azure AD conditional access would load the site in a web frame instead of redirecting the user back to the app.
- Fixed an issue where autofill did not work for sites opened from a secret.
- Fixed an issue when selecting an MFA+CheckOut - secret the authentication challenge would fail.
- Fixed an issue where the secret detail page was laid out incorrectly and the private key passphrase was unviewable.
- Fixed an issue where the Edit Password panel would disappear when a user clicked anywhere besides the Generate Password button.
- Fixed an issue where the pop-up header was cut off on Android devices.
- Fixed an issue on the Secrets list animation.
- Fixed an issue on the Delinea Mobile app where users were unable to authenticate on the same device when biometric was turned off.
- Fixed inconsistencies in the pop-up panel designs.

## 2.1.4 Release Notes

November 1st, 2023

### Features

- When a user has not configured biometric unlock on their device, or has disabled biometric unlock for the Delinea Mobile app, or has failed biometric unlock, the Delinea Mobile now calls on the secondary unlock

## Release Notes

mechanisms configured in the user's device.

- Users can now generate a password when adding a new secret.

## Usability Improvements

- The user name, email, and app version are now visible in the Profile view when accessed from Delinea Mobile's authenticator tab.
- Updated AWS, Windows, and Unix/Linux icons.
- Delinea Mobile now shows complete passwords with improved readability.

## Bug Fixes

- Fixed an issue where autofill search was not returning secrets.
- Fixed an issue where a "Check Out" option was displayed in the context menu for secrets with "Check Out + Comment" rules.
- Fixed an issue where the "Edit Secret Name" option was available before completing restrictions. App appeared to accept the change, but secret name was not updated.
- Fixed an issue where the search functionality was not working correctly.
- Fixed an issue where secrets were being auto-checked out when a user opened the "More Options" menu on the list.
- Fixed an issue where the "Continue" button was not disabled if one ticket system was selected all required fields were filled in, but were later changed.
- Fixed an issue with the ticket system functionality where the value in the ticket number field was not saved if the ticket system was changed.
- Fixed an issue with the ticket system functionality where it was possible to open a dropdown menu only if one ticket system was active.
- Fixed an issue with the ticket system functionality where asterisks were missing near required fields.
- Fixed an issue where saved profiles with activated biometry were not staying activated after updating to the new unlock system.

## iOS Specific

- Fixed an issue where some messages did not display the associated icon.

---

## 2.1.3 Release Notes (iOS Only)

*September 29th, 2023*

## Bug Fixes

- Fixed an issue where the password filling functionality was not working correctly and caused instability in the application.
  - Fixed an issue where the autofill functionality was not working correctly if the user did not log in to Delinea Mobile.
- 

## 2.1.2 Release Notes

September 26th 2023

### Features

- Users can now access secrets that are protected by DoubleLock directly from Delinea Mobile.
- Users can now access secrets that require a comment tied to a ticketing system directly from Delinea Mobile.

### Improvements

- The **Deactivate Secret** button is now available on both the *Secret Details* page as well as the *Secret List* page.
- The Settings and Profile popups were made smaller for improved usability.
- Additional spacing has been added between the icons on the top of the *Secret Details* page
- The search box for passcodes has been expanded to match the style in the rest of the application and be given enough space in the view
- The transitions between screens has been improved on iOS devices to open a new screen by animating from right to left. When you back out of the screen, it animates left to right.
- When creating a new secret, the **Generate** option is now available directly on any password field.
- The autofill instructions have been updated on iOS devices. Delinea Mobile now detects the iOS version and adjusts the instructions accordingly.
- The *Secret Details* context menu now includes an "Edit Name" menu item.
- New updates to the "Favorites" in the *Secrets* tab.
- The OTP codes are now displayed with separators for improved readability.
- When editing a password field, the process to show and edit the password has been streamlined. The "More Options" menu now displays the hidden password with a button option to show the password.
- Secret icons have been updated to squares with rounded corners
- Delinea Mobile's header has been updated to "DelineaMobile", as opposed to "DM".
- Recently viewed secrets now appear in the *Recent* tab.
- The ability to edit a secret name has been removed from the secret list. It now appears only in the "View Details" section.
- Folders that were added to *Favorites* are now displayed in the list with a yellow star in the *Favorites* tab.

## Bug Fixes

- Fixed an issue where secrets with workflows were not displaying the correct "Favorite" status.
- Fixed an issue where the "Remove from Favorites" menu option was not working correctly.
- Fixed an issue where users were unable to change/edit the name of a secret.
- Fixed an issue where the *Privacy Policy* selector was not aligned correctly.
- Fixed an issue where the Autofill spinner was infinitely spinning.
- Fixed an issue where the secret list tabs were positioned incorrectly.
- Fixed an issue where "Template" icons were missing for certain templates.
- Fixed an issue where the **Settings** buttons were not fully touchable.
- Fixed an issue where the pull to refresh was not working correctly.
- Fixed an issue where the *Secret Details*: field option icons were not aligned.
- Fixed an issue where Delinea Mobile would crash when users cleared the **Enter URL** field.
- Fixed an issue where "Check Out" item is displayed for a "Check Out" secret and a "Check Out+Comment" secret in context menu.
- Fixed an issue where the Templates panel was showing a "Select" option in the top right by default.

## iOS Specific

- Fixed an issue where the *Secrets* tab could not be scrolled.
- 

## 2.1.1 Release Notes

*August 14th, 2023*

### Features

- Customers can now access secrets guarded by multi-factor authentication.

### Bug Fixes

- Fixed an issue where the **Check out + Comment** functionality was not working correctly.
- Fixed an issue where users were not able to check in a secret that was checked out by another user.
- Fixed an issue where the **Approve/Deny** notifications were still briefly displayed after a user already made a selection.
- Fixed an issue where Delinea Mobile displayed a 0 in the toast message after the user tapped **Approve** in a notification.

## iOS Specific

- Fixed an issue where Delinea Mobile would crash after tapping **Back** on the **Secret Details** screen of a created secret from folders.
- Fixed an issue where Delinea Mobile would display an error when a users attempted to change the device name in Delinea Mobile.

## Android Specific

- Fixed an issue where notifications were not being properly displayed.
- 

## 2.1.0 Release Notes

July 18th, 2023

### Features

- Users are now able to access secrets that require a comment for checkout.

### Usability Improvements

- Users now have the ability to approve or deny notifications from the system notification tray on Android devices.
- The *Password* field has been expanded to display passwords up to 32 characters in length.
- The buttons on notifications now say **Approve** and **Deny**, instead of **Yes** and **No**.

### Bug Fixes

- Fixed an issue where the Restricted Access dialog was not docked to the bottom of the page.
- Fixed an issue where Delinea Mobile would display the folder selector after switching to and from a different app.
- Fixed an issue where the favorite icon was not displaying correctly.
- Fixed an issue where push notifications do not appear if Delinea Mobile is inactive.
- Fixed an issue where there user needs to complete biometric unlock twice after turning off the "Use Fingerprint to Unlock App" parameter.
- Fixed an issue where the TOTP codes would disappear after minimizing the application.

### Android Specific

- The **Back** button on Android devices now returns users to the prior screen, instead of an empty *Details* page.

### iOS Specific

- Fixed an issue with the layout of the *Authenticator* screen, where the search field was shifting and overlapping with the **Add Passcode** button.
- Fixed an issue where Delinea Mobile would crash when launching a URL from the *Details* panel.

## 2.0.11 Release Notes

*June 2, 2023*

### Android Specific

- Fixed an issue preventing the app from accessing Platform URLs when logging in

## 2.0.10 Release Notes

*May 23rd, 2023*

### Improvements

- Added an option to checkout a secret when checkout is required
- Added an option to check in a secret when checked out to the current user
- Delinea Mobile now retains the current screen when the user switches to a different app or the desktop and back to the app.

### Bug Fixes

- Fixed an issue where "Open" from step-up notification tray opens the app but doesn't display the notification
- Fixed an issue where users were able to approve MFA notifications from the tray without completing a biometric prompt

### Android Specific

- Fixed a push notification issue on Android
- Added functionality to allow users to approve or deny MFA requests directly from a notification in the notification tray

## 2.0.8 Release Notes

*April 5th, 2023*

### Improvements

- Message about disable camera is added
- Tapping search sets focus on the search field and show the keyboard
- Fixed inconsistent font styles
- Added a feature where the app hides the last viewed screen contents when the app is shown in the App Switcher



## Release Notes

### Bug Fixes

- Fixed a bug where the user was not able to change their password more than one time.
- Fixed graphical artifacts appearing after keyboard slides up.
- Fixed error allowing user to enter into the app after user taps logout.
- Fixed an issue where the slide-up menu obscured the system Navigation bar
- Fixed a bug where the mobile app navigated to the wrong screen when trying to create a new secret

## 2.0.7 Release Notes

*March 28th 2023*

### Improvements

- Delinea Mobile now hides the last viewed screen contents when the app is shown in the App Switcher

### Bug Fixes

- Fixed a bug where the mobile app navigated to the wrong screen when trying to create a new secret
- Fixed a bug where the app failed to show the login screen after entering the URL

### Android Specific

- Fixed an issue where the slide-up menu obscured the system Navigation bar

## 2.0.6 Release Notes

*March 23rd 2023*

### Improvements

- Users can now click **Generate Password** when editing any password field to generate a random password that satisfies the secret template's password requirements.

### Bug Fixes

- Fixed a crash when the user clicked the **Back** button from a restricted Secret.
- Fixed the checkmark on the list of Platform and Secret Server tenants to properly follow the current selection.

### Android Specific

- Fixed a bug where pressing **Back** after saving a secret created a new secret.
- Fixed an issue on some devices where the slide up menu on secrets was partially obscured by the virtual buttons.

## 2.0.5 Release Notes

*March 13th 2023*

### Improvements

- Added progress indicators during long waits from server
- Enabled the hide keyboard functionality when selecting a parent folder on Android devices

### Bug Fixes

- Fixed a display issue where popup panels were not the same size.
- Fixed an issue with alignment of elements in the **Settings** page
- Fixed an issue where the Authenticator icon was not highlighted when selected
- Fixed an error toast message that should not be displayed when logging into the app with biometrics disabled

### Android Specific

- Fixed an issue where the autofill process running in the main application caused the user to be logged out of application in some scenarios
- Fixed an issue where the **Continue** button was obscured by the OS system controls with some screen resolutions
- Fixed an issue where the **Cancel** and **Save** buttons were cut off
- Fixed an issue where app notifications were not displayed on the lock screen

## 2.0.0 Initial Release

*February 1st 2023:*

With this release, Delinea is rolling out the new **Delinea Mobile Application** for iOS and Android devices.

- For Delinea Mobile Overview refer to [Delinea Mobile Overview](#)